


Step 1 - Configuring PocketPC VPN Connection


Instructions for Configuring PocketPC 2002 for VPN Connection to the Fieldbook Server for **HP5150 Hand Held Devices**:

1 of 8



1. In PocketPC 2002, tap 'Start', tap, 'Settings'.

2 of 8




2. Tap the 'Connections' tab.
3. Tap the 'Connections'  icon.

3 of 8




4. Tap the “Edit my VPN servers”.

4 of 8



5. Tap, 'New'.

5 of 8



6. Enter, “fb.dot.utah.gov” in the “Host name/IP:” .

7. Tap, “PPTP” radial button.

8. Tap, “Next”.

6 of 8



9. Enter network (not field book) “User name:”, “Password” and “Domain”.

Enter the applicable “Domain” for your Region:

Region 1: **R1UDOT**

Region 2: **R2UDOT**

Region 3: **R3UDOT**

Region 4: **R4UDOT**

10. Tap, “Finish”.

7 of 8



11. “Tap and Hold” on the existing connection.

12. When the options appear, Tap, “Connect”.

NOTE: To connect, your device must be in the expansion pack and connected to the network.

8 of 8




13. Tap,  and wait for options to “Disconnect”.

This completes the VPN configuration setup. See, “**Step 2: Establishing a VPN Connection**” below.

Step 2: Establishing a VPN Connection

Instructions for **HP5150 Hand Held Devices:**


1 of 5



IMPORTANT: The iPAQ must be connected to UDOT's network via an Ethernet card, a modem, or a mobile phone (see the PDBS on-line Help's "Synchronizing Field Book and Project Accounting Data" section for connection information).

1. In PocketPC 2002, tap 'Start', tap 'Settings'.


2 of 5



2. Tap, 'Connections' tab.

3. Tap, 'Connections'  icon

3 of 5



4. Tap, “Manage existing connections”.

4 of 5



11. “Tap and Hold” on the existing connection.

12. When the options appear, Tap, “Connect”.

NOTE: See “Synchronizing Field Book and Project Information” in the PDBS “Help Topics”.

5 of 5



13. Tap,  and wait for options to “Disconnect”.